

*"No Delinquencer has ever made a mistake or distorted information. Every Delinquencer is, by any practical definition of the words, foolproof and incabale of **error**."*

# Walkthrough #1



Version 1.0.0

Kevin Lindley – 3rd June 2021

## Walkthrough #1: *First Contact*



### Overview

This walkthrough has been designed to get you using the basic features of the *Delinquencer*. We are going to use the *Delinquencer* to setup a very simple but recognisable 5 step sequence. By doing so you can get a feel for the different *Delinquencer* screens and parameters used. After following along you should be able to enter your own simple sequencer and then explore a little on your own before taking Walkthrough #2.

### Before you start

It is assumed that:

- You have installed the *Delinquencer* on your *Norns*.
- You have read through at least the first half of the *Delinquencer User Manual* and you have it handy for reference.

### Step by Step

Unfortunately, no one can be told what the *Delinquencer* is. You have to see it for yourself. OK, So let's get started .....

---

#### 1: Load the Init Patch

We are going to reset the *Delinquencer* to its "Init" patch.

Press the **[K2]** button until the *Note Entry* screen is displayed, see Figure 1 below:




Figure 1: Note Entry screen



# DELINQUENCER

Press and hold **[K1]** until the screen just shows a single row of active cells, see Figure 2:




Figure 2: Note Entry screen after pressing **[K1]**

This is the "init" patch which is just a very simple 8 note sequence. At any point you can always reset to the "init" patch by pressing and holding **[K1]** in the *Note Entry* screen.

## 2: Pausing and Starting the Sequencer

The sequencer is probably running, to stop it press the **[K1]** button (3 times) until you get to get back to the *Sequencer* screen.

Now, press the **[K3]** button. The sequencer will pause and the screen will display "Paused" and remind you to press **[K3]** to start it, see Figure 3 below:



Figure 3: Sequencer paused.

To restart it press the **[K3]** button.

Since we don't want the distraction of the sequencer running whilst entering a sequence of notes, press **[K3]** again to pause the sequencer.

## 3: Defining a New Pattern

Press the **[K2]** button to move to the *Note Entry* screen.

Press the **[K2]** button again, this time to move to the *PatternMaker* screen, see Figure 4 below:




Figure 4: PatternMaker screen

# DELINQUENCER

In the *PatternMaker* screen, turn [Encoder 2], until the *Pattern* parameter is highlighted (should currently be showing “8 Bit”).

Now turning the [Encoder 3], to the right, watch as the different patterns are displayed.

Keep turning [Encoder 3], until you get to a setting of “Seq5” then stop, see Figure 5 :



Figure 5: PatternMaker screen – “Seq5” pattern

Whilst we have the 5 cells “On” we want to change the *Neutron* parameter from *Rest* to **Skip**.

Using [Encoder 2], scroll until the *Neutron* parameter is highlighted (*Rest*) and then turn [Encoder 3] to the right until “Skip” is shown, see Figure 6 below:



Figure 6: Neutron parameter set to “Skip”

Leave the *Proton* parameter set to “On”.

## 4: Setting up the Sequencer Parameters

Now that we have setup the *PatternMaker*, we now need to enter the notes of our sequence and setup some other parameters.

Press the [K2] button, which takes us to the *Delinquer* screen (we will cover that later in the manual).

Notice, how pressing [K2] allows us to quickly loop around the 4 screens, see Figure 7 below:




Figure 7: Looping around the 4 screens.

# DELINQUENCER

Now press **[K2]** until you arrive back at the *Sequencer* screen.

Turn **[Encoder 2]**, to select the *BPM* parameter and then using **[Encoder 3]**, ensure that the *BPM* parameter it is set to **120**, see Figure 8 below:



Figure 8: BPM parameter set to "120"

Turn **[Encoder 2]**, to select the *Division* parameter and then using **[Encoder 3]**, set the *division* parameter to **1/1**, see Figure 9 below:



Figure 9: Division parameter set to "1/1"

Turn **[Encoder 2]**, and select the *Loop* parameter and using **[Encoder 3]**, set the *Loop* parameter to **Forward**, see Figure 10 below:




Figure 10: Loop parameter set to "Forward"

Turn **[Encoder 2]**, and select the *Scale* parameter and using **[Encoder 3]**, set the *Scale* parameter to **Chromatic** (keep turning Encode 3 to the right), see Figure 11 below:




Figure 11: Scale parameter set to "Chromatic"

Turn **[Encoder 2]**, and select the *Transpose* parameter and using **[Encoder 3]**, set the *Transpose* parameter to **2:0** (i.e. 2 octaves higher), see Figure 12 below:




Figure 12: Transpose parameter set to "2:0"

Everything is now set in the *Sequencer* screen.

## 5: Entering the Note Pitch Values

Press on the **[K2]** button to enter the *Note Entry* screen.




Figure 13: Note Entry screen

Using **[Encoder 1]**, turn it left until cell 1 (top left) is selected. Then, turn **[Encoder 2]**, to select the *Note* pitch parameter and using **[Encoder 3]**, select the *Note* pitch value of **D2**, see Figure 14 below:



Figure 14: Cell 1's note pitch set to D2

Using **[Encoder 1]** turn it right until cell 2 is selected. Using **[Encoder 3]**, select the *Note* pitch value of **E2**, see Figure 15 below:



Figure 15: Cell 2's note pitch set to E2

Turn **[Encoder 1]**, until cell 3 is selected. Using **[Encoder 3]**, select the *Note* pitch value of **C2**, see Figure 16 below:



Figure 16: Cell 3's note pitch set to C2

Turn **[Encoder 1]**, right until cell 4 is selected. Using **[Encoder 3]**, select the *Note* pitch value of **C1**, see Figure 17 below:



Figure 17: Cell 4's note pitch set to C1

Turn **[Encoder 1]** right until cell 5 is selected. Using **[Encoder 3]**, select the *Note* pitch value of **G1**, see Figure 18 below:



Figure 18: Cell 5's note pitch set to G1

## 6: Entering the Note Lengths

We now want to alter the note lengths, so using [Encoder 1], turn it left until cell 1 (far left) is selected. Then, turn [Encoder 2] to select the *Length* parameter and using [Encoder 3], select the *Length* value of 0.75.



Figure 19: Cell 1's note length set to 0.75

Using [Encoder 1], turn it right until cell 2 is selected. Using [Encoder 3], select a note *Length* value of 1.25, see Figure 20 below:



Figure 20: Cell 2's note length set to 1.25

Turn [Encoder 1], right until cell 3 is selected. Using [Encoder 3], select a note *Length* value of 2.0, see Figure 21 below:



Figure 21: Cell 3's note length set to 2.0

Turn [Encoder 1], until cell 4 is selected. Using [Encoder 3], select a note *Length* value of 1.25, see Figure 22 below:



Figure 22: Cell 4's note length set to 1.25

Turn [Encoder 1], until cell 5 is selected. Using [Encoder 3], select a note *Length* value of 4.0, see Figure 23 below:



Figure 23: Cell 5's note length set to 4.00

---

## 7: Playback Time

Press the **[K3]** button and listen to the sequence play.

Ok, so after successfully welcoming the mothership, pat yourself on your back. You just earned your first *Delinquencer* Scout Badge.



Just don't blame me if this entices you to go and buy a few 2500 Eurorack modules!

## Taking it Further

Now, some things to try on your own:

- Change the BPM.
- Try out different divisions.
- Make the Loop of this pattern go backwards.
- Try changing to the Natural Minor key ... so sad.
- Try transposing up a third.
- Go into the *Note Entry* screen and see if you can change the note probabilities, velocities and lengths.

## Conclusion

OK, so till now, you have taken the blue pill, the manual ends here, you wake up in your studio and you can use the *Delinquencer* as a simple sequencer.

But I recommend you take the red pill, you stay reading the *Delinquencer* manual, open up Walkthrough #2 and I show you how deep the rabbit hole goes.

Onward and downward we go.....